

Contents

pandas.Series Cheat Sheet	2
Retrieve spectra.....	2
Access spectra name.....	2
Access all transmittance (y-value)	2
Access all wavenumbers (x-value)	3
Access transmittance at a specific wavenumber.....	3
Access transmittance based on a slice of wavenumbers	3
Access the maximum transmittance and/or the corresponding wavenumber	4
Access the minimum transmittance and/or the corresponding wavenumber.....	4
Access local extrema of transmittance and the wavenumber	4
Do math on pandas.Series data.....	5
Import data from excel	6
Plot spectra	7
Export spectra to excel	7

pandas.Series Cheat Sheet

The spectra of containers read by sensor will be stored in `sensors_output` in `Pandas.Series` structure, here is a quick reference for frequently used API. For more information, please refer to pandas documentation on

<https://pandas.pydata.org/docs/reference/api/pandas.Series.html>

Retrieve spectra

```
>>> print(sensors_output)
```

```
# A nested dictionary includes Sensor Type, Sensor Location, Spectra of containers
```

```
{1: {'type': <SpectrumType.FTIR: 'FTIR'>, 'location': 500, 'spectrum': 3600  
-0.000053  
3598 -0.000049  
3596 -0.000015  
3594 0.000019  
3592 0.000051  
...  
1252 0.103183  
1250 0.102646
```

```
>>> print(sensors_output[sensor_id]['spectrum'])
```

```
# Spectrum is stored in pandas.Series structure. sensor_id should be set to 1.
```

```
3600 0.001952  
3598 0.001722  
3596 0.001528  
3594 0.001590  
...  
1252 0.253636  
1250 0.285266  
Name: PC, Length: 1176, dtype: float64
```

Access spectra name

```
>>> print(sensors_output[sensor_id]['spectrum'].name)
```

```
# Return the name of the Series. The name of the plastic is only passed to the sorting function in training mode. In testing mode, the name of the container will be 'unknown_plastic'
```

```
PC
```

Access all transmittance (y-value)

```
>>> print(sensors_output[sensor_id]['spectrum'].values)
```

```
# Return Series as ndarray or ndarray-like depending on the dtype.  
[0.00195171 0.00172183 0.00152848 ... 0.2209626 0.2536359 0.2852665 ]
```

Access all wavenumbers (x-value)

```
>>> print(sensors_output[sensor_id]['spectrum'].keys())

# Return alias for index.
Int64Index([3600, 3598, 3596, 3594, 3592, 3590, 3588, 3586, 3584, 3582,
...
          1268, 1266, 1264, 1262, 1260, 1258, 1256, 1254, 1252, 1250],
          dtype='int64', length=1176)
```

OR

```
# You could also convert it to a ndarray using .values
>>> print(sensors_output[sensor_id]['spectrum'].keys().values)
[3600 3598 3596 ... 1254 1252 1250]
```

Access transmittance at a specific wavenumber

```
>>> print(sensors_output[sensor_id]['spectrum'].get(3600))
```

```
# Get item from object for given key
0.001952
```

OR

```
>>> print(sensors_output[sensor_id]['spectrum'].iloc[0])
```

```
# Indexing for selection by position.
0.001952
```

OR

```
>>> print(sensors_output[sensor_id]['spectrum'].loc[3600])
```

```
# Access a group of rows and columns by label(s) or a boolean array.
0.001952
```

Access transmittance based on a slice of wavenumbers

Refer to Python **slice notation**:

<https://stackoverflow.com/questions/509211/understanding-slice-notation>

```
>>> print(sensors_output[sensor_id]['spectrum'].iloc[0:5])
```

```
3600    0.001952
3598    0.001722
3596    0.001528
3594    0.001590
3592    0.001453
```

```
Name: PC, dtype: float64
```

OR

```
>>> print(sensors_output[sensor_id]['spectrum'].loc[3600:3592])
```

```
3600    0.001952
3598    0.001722
3596    0.001528
3594    0.001590
```

```
3592    0.001453
Name: PC, dtype: float64
```

Access the maximum transmittance and/or the corresponding wavenumber

```
>>> spectrum = sensors_output[sensor_id]['spectrum']
>>> print(spectrum.idxmax(), spectrum.max())
```

```
# .max() Return the maximum of the values over the requested axis.
# .idxmax() Return index of first occurrence of maximum over requested axis.
```

```
1712 0.4544385
```

OR

```
>>> print(spectrum.sort_values(ascending=False))
```

```
# Sort a Series in ascending or descending order by some criterion.
```

```
1712    0.454439
1710    0.447742
1714    0.444016
```

```
...
```

```
3574   -0.000589
3576   -0.000607
```

```
Name: Polyester, Length: 1176, dtype: float64
```

Access the minimum transmittance and/or the corresponding wavenumber

```
>>> spectrum = sensors_output[sensor_id]['spectrum']
>>> print(spectrum.idxmin(), spectrum.min())
```

```
# .min() Return the minimum of the values over the requested axis.
# .idxmin() Return index of first occurrence of minimum over requested axis.
```

```
3576   -0.000607
```

OR

```
>>> print(spectrum.sort_values(ascending=True))
```

```
# Sort a Series in ascending or descending order by some criterion.
```

```
3576   -0.000607
3574   -0.000589
```

```
...
```

```
1714    0.444016
1710    0.447742
1712    0.454439
```

Access local extrema of transmittance and the wavenumber

You should import argrelextrema from scipy.signal module by using pip install scipy command. After downloading it, you could copy and paste the code to main.py to test argrelextrema function.

```
from scipy.signal import argrelextrema
import numpy as np
from matplotlib import pyplot as plt
```

```

def user_sorting_function(sensors_output):
    # random identification
    decision = {sensor_id: random.choice(list(Plastic)[0:-1]) for (sensor_id,
value) in sensors_output.items()}

    # retrieve spectrum
    sensor_id = 1
    spectrum = sensors_output[1]['spectrum']

    # exclude the blank spectra
    if spectrum.iloc[0] == 0:
        decision = {sensor_id: Plastic.Blank}
    else:
        # comparator = np.greater or np.less, stand for local maxima or
        minima
        # order = n, means how many points on each side to use for the
        comparison to consider
        # [0] at the end is to access the entire array of local extrema
        wavenumbers, based on the structure of return value
        n = 10
        iloc_max_wavenumbers = argrelextrema(spectrum.values,
        comparator=np.greater, order=n)[0]

        # Plot the spectrum
        spectrum.plot()

        # Plot the local maximum points on the spectrum you just plotted
        spectrum.iloc[iloc_max_wavenumbers].plot(title= spectrum.name,
        style="v", color="red")

        # Press Ctrl+C or Ctrl+Z in terminal to interrupt the plot windows
        plt.show()

```

Do math on pandas.Series data

- Average Spectrum


```

# First calculate the average value from raw_spectrum
>>> average_value = raw_spectrum.mean()
# Retrieve the list of wavenumbers from raw_spectrum
>>> wavenumbers_list = list(raw_spectrum.keys())
# Then create the corresponding list of average value (transmittance)
>>> average_value_list = [average_value for i in range(len(wavenumbers_list))]
# Construct an average spectrum using the average value list and
wavenumber list into a pandas.Series

```

```
>>> average_spectrum = pd.Series(data=average_value_list,
index=wavenumbers_list)
```

- Addition

```
>>> spectrum_addition = raw_spectrum + average_spectrum
```

- Subtraction

```
>>> spectrum_subtraction = raw_spectrum - average_spectrum
```

- Sum Squared Error (Summation, square, subtraction)

```
>>> import numpy as np
```

```
>>> np.sum(np.square(raw_spectrum - average_spectrum))
```

- Comparison

Greater than

```
>>> spectrum.gt(average_PP_spectrum))
```

Less than

```
>>> spectrum.lt(average_PP_spectrum))
```

Greater than or equal to

```
>>> spectrum.ge(average_PP_spectrum))
```

Less than or equal to

```
>>> spectrum.le(average_PP_spectrum))
```

These four return a pandas.Series with bool datatype

Concatenate two series

```
>>> import pandas as pd
```

```
>>> pd.concat([average_PP_spectrum, spectrum])
```

Return a pandas.Series with average_PP_spectrum attached by spectrum

Import data from excel

If you manipulated data in excel (e.g. set a threshold transmittance) and would like to import it to Python for comparison, you could refer to the following lines of codes

```
import random
```

```
from rcplant import *
```

```
import os
```

```
import pandas as pd
```

```
import numpy as np
```

```
def import_excel():
```

First need to put excel file 'demo_import.xlsx' under the same folder as main.py

```
data_file = os.path.join(os.path.dirname(__file__), 'demo_import.xlsx')
```

Use pandas to read the entire table

```
data_table = pd.read_excel(data_file, sheet_name=0, index_col=0)
```

```

# Use .loc[] the spectra you want to retrieve
average_spectrum = data_table.loc['PP_AVERAGE']

# OR
# You could also use raw spectrum and calculate the average by .mean()
raw_spectrum = data_table.loc['PP']
# Calculate the average value
average_value = raw_spectrum.mean()
# Retrieve wavenumbers list from raw_spectrum
wavenumbers_list = list(raw_spectrum.keys())
# Then create the corresponding average value (transmittance) list
average_value_list = [average_value for i in
range(len(wavenumbers_list))]
# Construct the average value list and wavenumber list into a
pandas.Series
average_spectrum_2 = pd.Series(data=average_value_list,
index=wavenumbers_list)
return average_spectrum_2

def user_sorting_function(sensors_output):
    # random identification
    decision = {sensor_id: random.choice(list(Plastic)) for (sensor_id,
value) in sensors_output.items()}

    # If you have made some data in excel (e.g. average PP spectrum)
    # and want to import to sorting function
    average_PP = import_excel()
    print(f'\nImport excel successfully: average_PP is {average_PP}')

    return decision

```

Plot spectra

Refer to here for matplotlib module: <https://pandas.pydata.org/pandas-docs/version/0.13.1/visualization.html>. A plot of spectra was attached to the end of Simulator Guide on Avenue

```

>>> from matplotlib import pyplot as plt
# using matplotlib module to show the plot
>>> plt.figure()
>>> sensors_output[sensor_id]['spectrum'].plot()
# .plot() Make plots of Series or DataFrame.
>>> plt.show()

```

Export spectra to excel

```

>>> sensors_output[sensor_id]['spectrum'].to_excel()
# .to_excel()

```